

OpenOffice.org

## Copyright

This document is Copyright © 2005, 2006 by its contributors as listed in the section titled **Authors**. You can distribute it and/or modify it under the terms of either the GNU General Public License, version 2 or later (http://www.gnu.org/licenses/gpl.html), or the Creative Commons Attribution License, version 2.5 or later (http://creativecommons.org/licenses/by/2.5/).

All trademarks within this guide belong to their legitimate owners.

## Authors

Jean Hollis Weber Daniel Carrera Ian Laurenson Iain Roberts Peter Kupfer Sigrid Kronenberger Agnes Belzunce Ken Byars Janet Swisher Lou Iorio Gary Schnabl

## Feedback

Maintainer: Gary Schnabl Please direct any comments or suggestions about this document to: authors@user-faq.openoffice.org

## Acknowledgments

Portions of the section on frames are taken from an article written by Bruce Byfield and originally published in *Linux Journal*.

## Publication date and software version

Published 12 November 2006. Based on OpenOffice.org 2.0.4.



You can download an editable version of this document from http://oooauthors.org/en/authors/userguide2/published/

## Contents

Copyright	i
Authors	i
Feedback	i
Acknowledgments	i
Publication date and software version	i
Introduction	1
Choosing a layout method	1
Setting up basic page layout using styles	3
Inserting a page break without switching the style	3
Defining a different first page for a document	4
Changing page orientation within a document	6
Setting up a landscape page style	6
Inserting a landscape page into a portrait document	7
Changing page margins	8
Using columns to define the page layout	9
Defining the number of columns on a page	9
Using a predefined column layout	10
Specifying the number of columns	10
Distributing text across columns	10
Formatting column width and spacing	10
Formatting separator lines	11
Reverting to a single-column layout	11
Changing the number of columns for existing text	11
Using frames for page layout	12
Creating frames	13
Moving, resizing, and changing frame attributes	14
Anchoring a frame	16
To Page	16
To Paragraph	16
To Character	16

As Character	16
Linking frames	
Using tables for page layout	
Example: Creating sideheads using tables	
Using sections for page layout	
Creating sections	21
Using the Section page	21
Naming sections	
Linking sections	
Write-protecting sections	
Password-protecting sections	
Hiding sections	23
Using the Columns page	
Using the Indents page	
Using the Footnotes/Endnotes page	
Customizing footnotes	
Customizing endnotes	
Using the Background page	
Saving a new section	
Editing and deleting sections	
Selecting a section	
Editing section attributes	
Deleting sections	
Editing the format of a section	
Updating links	
Updating links automatically	
Updating links manually	
Creating headers and footers	
Portrait headers on landscape pages	
Numbering pages	
Including the total number of pages	

#### Contents

Restarting page numbering	
Changing the format of page numbers	
Problems with restarting page numbering	
Solving the page count problem	
Numbering portrait and landscape pages	
Numbering the first page something other than 1	
Numbering pages by chapter	

## Introduction

Writer provides several ways for you to control page layouts:

- Page styles
- Columns
- Frames
- Tables
- Sections


This chapter describes these methods and some associated things:

- Headers and footers
- Numbering pages
- Changing page margins
- TipPage layout is usually easier if you select the options to show text, object, table, and<br/>section boundaries in Tools > Options > OpenOffice.org > Appearance and if you<br/>select the options for paragraph ends, tabs, breaks, and other items in Tools ><br/>Options > OpenOffice.org Writer > Formatting Aids.

## **Choosing a layout method**

The best layout method depends on what the final document should look like and what sort of information will be in the document. Here are some examples. Do not worry if all this does not mean much to you now. The techniques mentioned are all described in this chapter.


For a book similar to this user guide with one column of text, some figures without text beside them, and some other figures with descriptive text, use page styles for basic layout, and use tables to place figures beside descriptive text, when necessary.



#### Choosing a layout method

Use page styles (with two columns) for an index or other document with two columns of text where the text continues from the left-hand column to the right-hand column and then to the next page, all in sequence (also known as "*snaking columns*" of text). If the title of the document (on the first page) is full-page width, put it in a single-column section.

For a newsletter with a complex layout, two or three columns on the page, and some articles that continue from one page to some place several pages later, use page styles for basic layout. Place articles in linked frames and anchor graphics to fixed positions on the page, if necessary.



For a document with terms and translations to appear side-by-side in what appear to be columns, use a table to keep items lined up so you can type in both "columns".

## Setting up basic page layout using styles

In Writer, *page styles* define the basic layout of all pages, including page size, margins, the placement of headers and footers, borders and backgrounds, number of columns, and so on.

Writer comes with several page styles, which you can build on or modify, and you can define new (custom) page styles. You can have one or many page styles in a single document.

**Note** All pages in a Writer document are based on styles. If you do not specify a page style, Writer uses the *Default* page style.

To change the layout of individual pages, either define a new page style or use one of the techniques (sections, frames, or tables) described later in this chapter.

This chapter describes some uses of page styles. Some other uses are discussed in Chapter 6, "Introduction to Styles". The Page Style dialog box is covered in detail in Chapter 7, "Working with Styles".

**Tip** Any modifications of page styles, including the *Default* page style, apply only to the document you are working on. If you want the changes to be the default for all documents, you need to put the changes into a template and make that template the default template. See Chapter 10, "Working with Templates", for details.

## Inserting a page break without switching the style

In many documents (for example, a multi-page report), you may want the text to flow from one page to the next as you add or delete information. Writer does this automatically, unless you override the text flow using one of the techniques described earlier.

If you do want a page break in a particular place, for example, to put a heading at the top of a new page, here is how to do it:

- 1) Position the cursor in the paragraph you want to be at the start of the next page. Rightclick and choose **Paragraph** in the pop-up menu.
- 2) On the *Text Flow* page of the Paragraph dialog box (Figure 1), in the *Breaks* section, check **Insert**. Do *not* check **With Page Style**.

Paragraph					
		Backgro	ound		
Indents & Spacing	Alignment	Text Flow	Numbering 1	Tabs Drop Caps	Borders
		$\sim \sim$			
Breaks	$\sim$				
Insert	Type	Page	~	Position Before	~

V

Page number 0

Figure 1:	Inserting a	manual pag	e break	

With Page Style

3) Click **OK** to position the paragraph at the start of the next page.

## Defining a different first page for a document

Many documents, such as letters and reports, have a first page that is different from the other pages in the document. For example, the first page of a letterhead typically has a different header, as shown in Figure 2, or the first page of a report might have no header or footer, while the other pages do. With OOo, you can define the style for the first page and specify the style for the following page to be applied automatically.

	0.0539-0524	OpenOfficerat
On other	JAIN HIRE MADE	operation
OpenOffice.org	PO Box 000 C10, 2128 9000 Ana festio	with here its available . Or subdive a behaved that the masses a behave right with Downer functions with we will be an any set data. Consider with the set it behave all considering with set it. U. U. Spense were not set of the set of constant data constant of the sets.
Min / Communitient Disor Labitance Chin, State Wold Controly	2002	In concentration, in the same a same of a loss of same and a same
		Peganta
	Collide 1 14, 2004	
Dever Sit.		Jean Hullit Vieter
equation. One equation introduce to definition the indigate approximation spectroscolers oper constitution of primer than dispets in a constitution with the primer discovery interfaciency indications of the place that mapping. Then there as the transmission of the place of place to the most thin computer, mapped, with equal the transmission of the place of the place of the equation.	De, dein, Utiget, eins eget poen a setta utbe, begistaret, gann, activite ere, beter, Kere stanet mit gann wie fachlich H.	
In the operate despite of the Chine refers. A time commonly achieved on the part of the chine data of the entropy of the chine of the chine of the chine trapped data points. The chine part of the chine of the constant on any other a trans place of the chine of the Chine on affile the chine of the chine of the chine of the Chine on affile the chine of the	diming the spane, consideration of the other is detained. Moreover, and an detailed in proceeding to be added as of the proceeding to be an advanced.	
The part that could not also, dense theory, not to optime. If not interpreter prime about the data applies many that and has part interprint symmetries. In particu- tions of the single prime structure, in these subtracts plan of the structure applies. The structure of the single structure applies. The structure is the single structure of the single s. Danses with first. This parts with single structure and structure is the single structure structure structure.	1 See Section (1. a) How Surger (1. c) is reaction (1. c) Her (1. c) (1. c) (1. c) (1. c) is definited. France (1. c) (1. c) (1. c) for the state section (1. c) (1. c) (1. c) for the state section (1. c) (1. c) (1. c) is reacted by realized on contrary satisfies).	
Deser nayth Smeathn light, San operated, W Class are, Robit forface percentioned perce. Inform light off, Robit elimentation, Adde etc. In Inford Jack and Robit elimentation and are to be lined Jack and Robit elimentation and are to be described and	nen beim "Hene dichm erfafte ent, mper int jurit, felfahlunger an alle.	

Figure 2: Letterhead with different page styles for first and following pages

As an example, we can use the *First Page* and *Default* page styles that come with OOo. Figure 3 shows what we want to happen: the first page is to be followed by the default page, and all the following pages are to be in the *Default* page style.




Figure 3: Flow of page styles

To set up this sequence:

- Open the Styles and Formatting window. (You can choose one of the following: click the Styles and Formatting icon located at the left-hand end of the object bar, choose Format > Styles and Formatting, or press *F11*.)
- 2) On the Styles and Formatting window (Figure 4), click on the **Page Styles** icon (fourth from the left) to display a list of page styles.
- 3) Right-click on First Page and select Modify from the pop-up menu.

Styles and	l Formatting		×
T, A	d B E	۵ 🗊 🔦	•
Default Endnote Envelope First Page Footnote	<u>N</u> ew…		
HTML Index Left Page Right Page	Modify		
All		~	]

Figure 4: Modifying the First Page style

4) On the *Organizer* page of the Page Style dialog box (Figure 5), look at the *Next Style* property. This property defines what the page style for the next page will be. It should be set to **Default**, but if it is not, you can change the next style by clicking on the drop-down button and choosing **Default** from the list of page styles.

Page Style: First Page				
Organizer Page	Background Header Foot	er Borders Columns Fo	ootnote	
Name First Page				
Ne <u>x</u> t Style	Default		~	
Linked with		Click to display list of		
<u>C</u> ategory	Custom Styles	page styles	*	

*Figure 5: Setting the Next Style property for a page style* 

- 5) On the other pages of this dialog box, you can turn on or off the header and footer for the first page and define other characteristics, such as columns, a page border, or a page background. For more information, see Chapter 7, "Working with Styles".
- 6) Click **OK** to save the changes.
- **Note** You can override the *Next Style* property by manually inserting a page break and specifying a page style or by starting a page with a paragraph or table that has its own page style property defined. These techniques are described in "Inserting a landscape page into a portrait document" on page 7.

## Changing page orientation within a document

A document can contain pages in more than one orientation. A common scenario is to have a landscape page in the middle of a document, whereas the other pages are in a portrait orientation. Here are the steps to achieve it.

#### Setting up a landscape page style

- 1) Note the page style that is current and the margin settings. (You can find the margin settings on the *Page* page of the Page Style dialog box, as shown in Figure 8.)
- 2) Create a new style. (Right-click on the current page style in the Styles and Formatting window and choose **New**, as shown in Figure 6.)

Styles and Formatting	×
t A D B B	• 🖻 🔇
Default Endnote <u>M</u> odify First Page Footnote HTML Index Left Page Right Page	
All	~

Figure 6: Starting a new page style

3) On the Organizer page of the Page Style dialog box (Figure 7), name (by typing in the Name field) this new style Landscape and set the Next Style property to Landscape (to allow for having more than one sequential landscape page).

Page Style	
Organizer Pa	ge Background Header Footer Borders Columns Footnote
<u>N</u> ame	Landscape
Ne <u>x</u> t Style	Landscape 🗸 🗸 🗸
Linked with	×
Category	Custom Styles

Figure 7: Naming the new style and setting the next page style to Landscape

- 4) On the *Page* page of the Page Style dialog box (Figure 8), set the *Orientation* to **Landscape**. The width and height attributes of the page will automatically change.
- 5) Change the margins so that they correspond with the margins of the portrait page. That is, the portrait top margin becomes the landscape left margin, and so on.
- 6) Click **OK** to save the changes.

Page Style				×
Organizer Page	Background Heade	er Footer Borders	Columns Footnote	
Paper format —				
Eormat	A4 💌			
Width	29.70cm 🚖			
<u>H</u> eight	21.00cm 📚			
Orientation	O Portrait			
	<ul> <li>Landscape</li> </ul>	Paper <u>t</u> ray	[From printer settings]	~
Margins		Layout settings		
Left	3.00cm 🚖	Page layout	Right and left	~
<u>R</u> ight	2.50cm 📚	For <u>m</u> at	1, 2, 3,	~
Тор	2.00cm 🚖	Register-true		_
Bottom	2.00cm 🚖	Reference <u>S</u> ty	/le	~

*Figure 8: Setting orientation and margins for a landscape page* 

#### Inserting a landscape page into a portrait document

Now that you have defined the Landscape page style, here is how to apply it.

- 1) Position the cursor in the paragraph or table at the start of the page that is to be set to landscape. Right-click and choose **Paragraph** or **Table**, respectively, in the pop-up menu.
- 2) On the *Text Flow* page of the Paragraph dialog box (Figure 9) or the Table Format dialog box (Figure 10), select Insert (or Break for a table) and With Page Style. Set the *Page Style* property to Landscape. Click OK to close the dialog box and to apply the new page style.

Paragraph					X
	Backgro	ound			
Indents & Spacing Alignment	Text Flow	Numbering	Tabs	Drop Caps	Borders
Hyphenation					
Breaks	Page	~	Bo	osition Before	
With Page Style	Default		Page <u>n</u> u	umber 0 🚦	
Options	HTML	^		_	
🗌 Do not split paragraph <	Landscape	$\rightarrow$			_
Keep with next paragraph	Left Page Right Page	~			

Figure 9: Specifying a page break before a paragraph

Table Format				×
Table Text Flow	Columns Bo	rders Background		
Text Flow				
🗹 <u>B</u> reak			🔘 Col <u>u</u> mn	
		⊙ Be <u>f</u> ore	◯ <u>A</u> fter	
With Page St	yle	Landscape	Page number	0 📚
Allow table to	o split across p	bages ar Default	^	
		First Page		
Keep with ne	ext paragraph	Left Page Right Page	~	

Figure 10: Specifying a page break before a table

- 3) Position the cursor in the paragraph or table where the page is to return to portrait orientation and change the properties of that paragraph or table properties so that *With Page Style* is the portrait page style that was used before the *Landscape* page style.
- 4) Click **OK** to return to the previous portrait page style.

**Tip** If you need the headers or footers on the landscape pages to be in portrait orientation, see "Portrait headers on landscape pages" on page 31.

## **Changing page margins**

You can change page margins in two ways:

- Using the page rulers—quick and easy, but does not have fine control.
- Using the Page Style dialog box—can specify margins to two (fractional) decimal places.
- **Note** If you change the margins using the rulers, the new margins affect the page style and will be shown in the Page Style dialog box the next time you open it.

To change margins using the rulers:

- 1) The shaded sections of the rulers are the margins (see Figure 11). Put the mouse cursor over the line between the gray and white sections. The pointer turns into a double-headed arrow.
- 2) Hold down the left mouse button and drag the mouse to move the margin.
- **Tip** The small arrows on the ruler are used for indenting paragraphs. They are often in the same place as the page margins, so you need to be careful to move the margin marker, not the arrows. Place the mouse pointer between the arrows and, when the pointer turns into a double-headed arrow, you can move the margin (the indent arrows will move with it).




Figure 11: Moving the margins

To change margins using the Page Style dialog box (Figure 8):

- 1) Right-click anywhere on the page and select Page from the pop-up menu.
- 2) On the Page page of the dialog box, type the required distances in the Margins boxes.

## Using columns to define the page layout

You can use columns for page layout in several ways:

- Define the number of columns on a page, using page styles.
- Switch between one-column and multiple-column layouts on the same page.
- Select existing text and change the number of columns.

## Defining the number of columns on a page

It is a good idea to define your basic page style (such as *Default*) with the most common layout to be used in your document, either single-column or multiple-column. You can then either define extra page styles for pages with different numbers of columns or use sections (described in "Using sections for page layout" starting on page 21) for pages or parts of pages with different numbers of columns.

To define the number of columns on a page:

- 1) Choose **Format > Columns** or go to the *Columns* page of the Page Style dialog box.
- 2) On the Columns dialog box (Figure 12), choose the number of columns and specify any spacing between the columns and whether you want a vertical separator line to appear between the columns. You can use one of Writer's predefined column layouts, or you can create a customized column layout. The preview box, located to the right of the *Settings* area, shows how the column layout will look.
- 3) Notice the *Apply to* box on the right-hand side of the dialog box. In this case, the changes are being applied to the *Default* page style.
- 4) Click **OK** to save the changes.

Columns						
Settings						ОК
<u>C</u> olumns						Cancel
3 🏝						
				L		Help
Width and spacing	g —					Apply to
Column		<u>1</u>	2	3	+	Page Style: Def
Width		5.67cm 🚖	5.27cm 🚖	5.27cm 🚖		
Spacing		0.40cm	D.40cm	n 🚖		
		📃 Auto <u>W</u> idth				
Separator line —						
Line	0.	05 pt 💌				
Height	95%					
Position	Тор	~				

Figure 12: Defining the number of columns on a page

#### Using a predefined column layout

The *Settings* area displays five predefined column layouts. To use one of them, click the desired layout.

#### Specifying the number of columns

If you prefer to create a customized column layout, you must specify the number of columns that you want. Enter the desired number in the *Columns* box in the *Settings* area.

#### **Distributing text across columns**

You can distribute text across the columns in one of two ways:

- Evenly—If you choose to distribute text evenly, Writer will fill the first line of each column, followed by the second line of each column, and so on.
- **Newspaper-style**—If you choose to distribute text newspaper-style, Writer will fill the columns one at a time, beginning with the first column.

To distribute text evenly, check the **Evenly distribute contents to all columns** check box in the *Settings* area. Clear this check box if you want to distribute text newspaper-style.

**Note** This check box is not always displayed in the *Settings* area. See "Changing the number of columns for existing text" on page 11.

#### Formatting column width and spacing

To create evenly-spaced columns that are all the same width, check the **AutoWidth** check box in the *Width and spacing* area.

To customize the width and spacing of the columns, follow these steps:

- 1) In the Width and spacing area, clear the AutoWidth check box.
- 2) On the *Width* line, enter a width for each column.
- 3) On the *Spacing* line, enter the amount of space that you want between each pair of columns.

If you specify more than three columns, use the arrow keys on the *Column* line to scroll among the columns.

#### Formatting separator lines

To display separator lines between the columns:

- 1) Eighteen separator line options exist: None or various lines of thicknesses which range from 0.05 to 9 pt). From the *Line* drop-down list in the *Separator line* area, select the type of line that you want. (1 pt = 1 point = 1/12 pica =  $1/_{72}$  inch =  $127/_{360}$  mm = 0.3527 mm.)
- 2) The default format is for the separator lines to have the same height as the columns. If you want the separator lines to be shorter than the columns, use the *Height* box to enter the height of the separator lines as a percentage of the height of the columns. For example, if you enter 50%, the separator lines will be half as high as the columns.
- 3) If you entered a height of less than 100%, use the *Position* drop-down list to select a vertical alignment for the separator lines. The vertical-positioning options are: **Top**, **Centered**, or **Bottom**.

#### Reverting to a single-column layout

To revert to a single-column layout, go to the *Settings* area and either reset the number in the *Columns* box to 1 or click the single-column layout icon.

## Changing the number of columns for existing text

You might want some parts of a page to have one column and other parts of the page to have two or more columns. For example, you might have a page-width headline over a three-column news story.

You can create columns and then type or paste text into them, or you can select some existing text and change the number of columns for displaying it.

When you select text and change the number of columns for that text, Writer turns the selected text into a *section*, as described in "Using sections for page layout" on page 21.

Figure 13 shows the Columns dialog box for a selection. Notice that the *Apply to* box on the right-hand side has **Selection** highlighted and an extra check box (**Evenly distribute contents to all columns**) appears in the upper left-hand part of the dialog box.

As you add text to the section, you will see that the text flows from one column to the next so that all the columns adjust to the same height. If this is not what you want, click anywhere in the section, then choose **Format > Columns** to reopen the Columns dialog box, deselect the **Evenly distribute contents to all columns** check box, and click **OK** to effect the change.

# **Tip** Choose View > Nonprinting Characters (or press Ctrl+F10) to display end of paragraph markers (¶). Often, unexpected behavior of columns is due to extra paragraphs that are normally invisible to the user but are taking up space.

Columns						
Settings						ОК
Columns 2 📚						Cancel
🗹 Evenly distri	bute contents	<u>t</u> o all columns				Help
Width and spaci	ng					Apply to
Column	(*)	<u>1</u>	2	<u>3</u>	+	Selection 🗸
Width		8.25cm 😂	8.25cm 😂	\$		Selection
Spacing		0.50cm	n 🌲	<b>\$</b>		Page Style: Default
		🗹 Auto <u>W</u> idth				
Separator line –						
Line	None	<b>~</b>				
H <u>e</u> ight	100%	\$				
Position	Тор	×				

Figure 13: Specifying columns for a selection

## Using frames for page layout

Frames can be very useful when producing a newsletter or other layout-intensive documents. Frames can contain text, tables, multiple columns, pictures, and other objects.

Use frames when you need to:

- Position something in a particular place on a page, for example, a logo or a "stop press" news box in one corner of a page.
- Allow text on one page to continue on another page somewhere else in the document (other than the next page), by linking the content of one frame to another so the contents flow between them as you edit the text.
- Wrap text around an object, such as a photograph.

Because OpenOffice.org does not allow you to define page styles with recurring frames, consider doing some quick sketches of the basic page layouts you need, indicating the approximate positions of different frames and their purposes. Try to keep the number of different page layouts as low as possible in order to avoid chaos in your design.

Pay special attention to the positioning of frames. Many of the predefined styles default to a center alignment. This is the lowest common denominator of design; centering all frames looks reasonably good in most cases but is rarely the best choice.

One of the most visually effective ways to position a frame is to align its left margin with that of the paragraph above it. To achieve this effect, insert the frame in a blank paragraph of the same style as the paragraph above. Then, select **Insert > Frame > Type > Position > Horizontal > From Left** to position the frame exactly where you want it.

You also should think about the type of wrap and the spacing between the frame and text. Instead of cramming a frame close to the text, use the *Wrap* tab to place some white space between them.

You can format frames individually or define and apply frame styles (see Chapter 7, "Working with Styles").

**Tip** The Help uses the phrase "text frame" for two quite different things with very different characteristics: frames (as discussed here) and text objects, which are drawing objects similar to lines and boxes.

### **Creating frames**

You can create a frame in several ways, depending on your needs.

- Choose **Insert > Frame**) to create an empty frame. The Frame dialog box (Figure 15) appears. You can click **OK** and come back to customize it later, or you can set the frame's characteristics at this stage.
- Select text or a graphic, choose **Insert > Frame**, and click **OK** to create a frame containing the selection. The selected text is automatically deleted from the normal text flow and inserted into the frame, and the Frame dialog box appears.
- Insert a picture or other object by selecting **Insert > Picture > From file** or **Insert > Object** to start the process to insert a picture or object. The item inserted automatically appears in a frame, but the Frame dialog box does not appear.
- Use the **Insert Frame Manually** icon on the Insert toolbar (go to **View > Toolbars** > **Insert** to display it), select the number of frames in the drop-down menu, and drag the mouse to draw the frame.

Insert							<b>▼</b> ×
<b>Ⅲ</b> -	🚯	<u> 👷</u> 🖉	🖉   🗯	va 📑 -	🗏 🖂 🕶	Insert Index	🎨 + 🖪 🔌
		Cancel					

Figure 14: Using an icon on the Insert toolbar to create a frame

When you release the mouse button, a box appears where the cursor is located in the document. This box represents the frame: an area isolated from the main document.



To add content to a frame, first deselect the frame by clicking somewhere else on the page. Then, click inside the frame so that the cursor shifts its focus there. Now add content just like you would on the main page. When you are done, deselect the frame.

## Moving, resizing, and changing frame attributes

When an object is added to Writer, it is automatically enclosed in a frame of a predetermined type. The frame sets how the object is placed on the page, as well as how it interacts with other elements in the document. You can edit the frame by modifying the frame style it uses or by using a manual override when a frame is added to the document. Frame styles are discussed in Chapter 7, "Working with Styles".

To change the size or location of a frame, first select the frame, then use either the mouse or the Frame dialog box (Figure 15). Using the mouse is faster but less accurate. You might use the mouse for gross layout and the dialog box for fine-tuning.

You can resize the frame manually (by clicking on the green squares and dragging to the appropriate size) or start adding content to it (the frame will resize automatically if you, for example, add a large picture to it) or go back to the Frame dialog box and set the size and other characteristics.

To change the location of the frame using the mouse, drag and drop one of the edges or having the cursor anywhere within the frame. (The I-bar cursor changes to a four-headed arrow when properly positioned for a drag-and-drop move.) To change the size of the frame, drag one of the handles. Drag a handle on one of the sides to enlarge or reduce the text frame in one dimension only; drag a corner handle to enlarge or reduce it in both dimensions.


These resizing actions distort the proportions of the frame. Holding down the *Shift* key while dragging one of the handles makes the frame keep the same proportions.

You can open the Frame dialog box (Figure 15) at any time by selecting the frame, rightclicking, and choosing **Frame** from the pop-up menu.

Frame				
Type Options Wr	ap Hyperlink Borde	ers Background	Columns Macr	o
Size		Anchor		
<u>W</u> idth	3.71cm 📚	🔵 To gage		
📃 Relatįve		💿 To paragra	ip <u>h</u>	
A <u>u</u> tomatic		🔵 To cha <u>r</u> act	er	
H <u>e</u> ight (at least)	1.31cm 凄	O <u>A</u> s charact	er	
Relative				
Auto <u>S</u> ize				
Keep ratio				
Position				
Horizontal F	From left 💽 t	oy 0.28cm 😤	to Paraç	graph area 🛛 💌
Mirror on e	ven pages			
<u>V</u> ertical F	From top 💽 🛓	2y 0.81cm 😤	t <u>o</u> Margi	in 💌
Follow te <u>x</u> t	: flow			
		ОК	Cancel	Help Reset

Figure 15: Frame dialog box

To remove the default border on a newly created frame, open the Frame dialog box, go to the *Borders* page, and under *Line*, select **None**. Alternatively, you can assign a borderless frame style to the frame; see the Chapter 7, "Working with Styles", for information on frame styles.



ype Options Wrap Hyp	erlink <b>Borders</b>	Background Co	lumns Macro	
Line arrangement	Line		Spacing to co	ntents
<u>D</u> efault	Style		Left	0.15cm 📚
	- None -	— 0.05 pt	Right	0.15cm 🚖
User-defined		— 0.50 pt 🔳	Tob	0.15cm 📚
+ +		- 1.00 pt 2.50 pt	Bottom	0.15cm 📚
		= 4.00 pt	Synchro	onize

Figure 16: Removing the border from a frame

## Anchoring a frame

Using the Frame dialog box (or by right-clicking and pointing to **Anchor**), you can anchor a frame to a page, paragraph, or character, or you can anchor it as a character.

### To Page

The frame keeps the same position in relation to the page margins. It does not move as you add or delete text. This method is useful when the frame does not need to be visually associated with a particular piece of text. It is often used when producing newsletters or other documents that are very layout-intensive.

#### **To Paragraph**

The frame is associated with a paragraph and moves with the paragraph. It may be placed in the margin or another location. This method is useful as an alternative to a table for placing icons beside paragraphs.

#### **To Character**

The frame is associated with a character but is not in the text sequence. It moves with the paragraph but may be placed in the margin or another location. This method is similar to anchoring to a paragraph.

#### As Character

The frame is placed in the document like any other character and, therefore, affects the height of the text line and the line break. The frame moves with the paragraph as you add or delete text before the paragraph. This method is useful for adding a small icon in sequence in a sentence. It is also the best method for anchoring a graphic to an empty paragraph so it does not move around the page in unexpected ways.


## Linking frames

You can link several frames to each other even when they are on different pages of a document. The contents will automatically flow from one to the next. This technique is very useful when designing newsletters, where articles may need to be continued on a different page.

To link one frame to another:

- 1) Select the frame to be linked from.
- 2) Click the Link Frames icon <sup>(1)</sup> on the object bar.
- 3) Click the next frame in the series (which must be empty).

When a linked frame is selected, any existing links are indicated by a connecting line, as shown in Figure 17.





The height of a frame that is being linked from is fixed; you can change this height manually or by using the Frame dialog box, but it does not automatically adjust to the size of the contents (that is, the AutoHeight attribute is disabled). Only the last frame of a chain can adapt its height to the content.

The *Options* page of the Frame dialog box (Figure 18) shows the names of the selected frame and any frames it is linked to or from. You can change this information here. On this page, you can also select check boxes to protect the contents, position, and size of the frame.

ame								
ype Options	Wrap	Hyperlink	Borders	Background	Columns	Macro		
<u>N</u> ame			Frame1					
Previous link			<none></none>					~
<u>N</u> ext link			Frame2					~
Protect	;							
Position								
Properties	in read-o	only docume	nt					
🗹 Prin <u>t</u>								
<u>T</u> ext directio	n	Use	superordir	nate object sett	tings			~
				ок	Cancel		p [	<u>R</u> eset

Figure 18: Options page of the Frame dialog box

On the *Hyperlink* page (Figure 19), you can specify the file for the hyperlink to open. This file can be on your machine, a network, or the Internet.

Frame						
Type Options \	Wrap Hyperlink	Borders	Background	Columns	Macro	
Link to	_	_			_	
URL						Browse
Name						
Erame			~			
Image map —						
Server-side	e image map					
Client-side	image map					

Figure 19: Hyperlink page of the Frame dialog box

The *Wrap*, *Borders*, *Background*, *Columns*, and *Macro* pages of the Frame dialog box are the same as those for frame styles. Refer to the Chapter 7, "Working with Styles", for details.

## Using tables for page layout

Writer's tables can serve several purposes, such as holding data as you might see it in a spreadsheet, lining up material, and creating more complex page layouts. For information about using tables of data, see Chapter 9, "Working with Tables".

This topic describes how to achieve some common layouts by using tables.

## Example: Creating sideheads using tables

Sideheads and marginal notes are commonly used in documents from resumes to computer user guides. The main body of the text is offset to leave white space (usually on the left-hand side) in which the sideheads or notes are placed. The first paragraph is aligned beside the sidehead, as in Figure 20.

Example of a sidehead	In some cases you may want to put only one or two paragraphs in the table itself and the rest of the text and graphics in ordinary paragraphs (formatted to line up with the paragraphs in the table) so that text and graphics will flow more easily from one page to another when you add or delete material.
	In other cases, you might put each paragraph in a separate row of the table and allow the table to break between pages.

Figure 20: Example of a sidehead

**Note** Sideheads can also be created by placing text in a frame using the *Marginalia* frame style, as described in the Chapter 7, "Working with Styles".

To create a table for use with a sidehead:

- 1) Place the cursor where you want the table to appear and choose **Insert > Table** (*Ctrl+F12*).
- 2) In the Insert Table dialog box (Figure 21), define a one-row, two-column table with no border and no heading. Click **OK** to create the table.

Insert Table		
Name Size	Sidehead1	OK Cancel
<u>C</u> olumns <u>R</u> ows Options	2	Help
☐ Heading ✓ Repeat <u>The first</u>		
📃 <u>D</u> on't split ta	able	
AutoEorn	nat	

Figure 21: Defining a two-column borderless table with no header

3) Position the cursor over the central dividing line in the table. The cursor turns into a double-headed arrow. Left-click and drag to resize the columns. Alternatively, right-click and choose Table from the pop-up menu; on the *Columns* page (Figure 22), make the columns the required width.

Table Format		Þ
Table Text Flow Column	Borders Background	
Adapt table width		
Adjust columns propor	ionally	
Remaining space	0.00cm	
Column width		
+ 1	2	
3.00cm 😤 14.000	m 🐑 🔅 🔅	

*Figure 22: Defining a two-column table to line up with text offset at 3 cm* 

4) On the *Table* page of the Table Format dialog box (Figure 23), in the *Spacing* section, make the *Above* and *Below* values the same as the *Top* and *Bottom* spacing you have defined for ordinary paragraphs of text. Click **OK** to save your settings.

able Text Flow	Columns Borders Background		
Properties			Alignment
<u>N</u> ame	Sidehead1		Automatic
Width	17.00cm 🔤 🗌 Relative		◯ <u>L</u> eft
Spacing		_	_ O <u>F</u> rom left
Left		0.00cm 😂	🔘 Right
-			◯ <u>C</u> enter
Right		0.00cm 😒	O <u>M</u> anual
<u>A</u> bove		0.20cm 📚	
Below		0.20cm 🚖	

*Figure 23: Defining the space above and below a table* 

**Tip** To check the top and bottom spacing for ordinary paragraphs:

- 1) Position the cursor in a paragraph and press *F11* (unless the Styles and Formatting window is already open). Check that the Styles and Formatting window shows paragraph styles (top left button).
- 2) The current style should be highlighted. If no paragraph style is highlighted, select **All Styles** in the bottom drop-down list. Right-click on it and select **Modify** from the pop-up list.
- 3) Go to the *Indents & Spacing* page and look in the *Spacing* area for the values in *Above paragraph* and *Below paragraph*.

You may also want to turn off number recognition so that Writer will not try to format numbers if you want them to be plain text. To turn number recognition off:

- 1) Right-click in the table and then click Number Format on the pop-up menu.
- 2) On the Number Format dialog box (Figure 24), make sure the *Category* is set to **Text**. Click **OK**.

Number Format					
<u>C</u> ategory		F <u>o</u> rmat	Language	_ ОК	
Currency Date Time Scientific Fraction Boolean Value Text		0	Default		
Date				Cancel	
Time					
Scientific					
Fraction	=			Help	
Boolean Value					
Text			0		
	<b>~</b>				

Figure 24: Setting number format to Text

**Tip** If you use this table format often, you may want to save it as AutoText, as described in Chapter 3, "Working with Text". Select the table (not just the contents) to assign the shortcut.

## Using sections for page layout

A section is a block of text that has special attributes and formatting. You can use sections to:

- Write-protect text
- Hide text
- Dynamically insert the contents of another document
- Add columns, margin indents, a background color, or a background graphic to a portion of your document
- Customize the footnotes and endnotes for a portion of your document

## **Creating sections**

To create a section:

- 1) Place the cursor at the point in your document where you want to insert the new section. Or, select the text that you want to place in the new section.
- 2) From the main menu, choose **Insert > Section**. The Insert Section dialog box opens.
- 3) Click the **Section** tab, if it is not already displayed. (See Figure 25.)

The Insert Section dialog box has five tabbed pages:

- Use the *Section* page to set the section's attributes.
- Use the *Columns* page to format the section into columns.
- Use the *Indents* page to set indents in the right and left margins of the section.
- Use the *Background* page to add color or a graphic to the section's background.
- Use the *Footnotes/Endnotes* page to customize the section's footnotes and endnotes.

At any time, you can reset a tabbed page to its default settings by clicking the **Reset** button. (Note, however, that you cannot reset the *Section* page. If you wish to undo changes to the *Section* page, you must do so manually.)

## Using the Section page

Use the Section page (Figure 25) to set the attributes of the current section.

#### **Naming sections**

Writer automatically enters a name for the current section in the top box of the *New section* area. To change the name, select it and type over it. The name is displayed in the *Sections* category of the Navigator window. If you give your sections meaningful names, you can navigate to them more easily.

Insert Se	ection						
Section	Columns	Indents	Background	Footnotes/End	notes		
New se	ction ——		— Link —				
βect	ion1		Link				_
			<u>F</u> ile nam	ie			
			Section				~
			Write prot				
				Wit <u>h</u> password			
			Hide Hide				
			<u>W</u> ith Co	ndition			
			Properties	able in read-only	document		
				Insert	Cancel	Help	Reset

Figure 25: Inserting a section using the Insert Section dialog box

#### Linking sections

You can insert the contents of another document into the current section and then have Writer update the section whenever the other document is updated. This is called *linking* the section to the other document.

To link the current section to another document, follow these steps:

1) In the *Link* area (see Figure 26), check the **Link** check box.

Link	
🗹 Link	
<u>F</u> ile name	
Section	¥

*Figure 26: Linking sections* 

- 2) Click the (...) button to the right of the *File name* field. The Insert dialog box opens.
- 3) Find and select the document you want to insert and then click the Insert button. The Insert dialog box closes and the name of the selected document appears in the *File name* field.
- 4) If you want to insert only a section of the selected document, select the desired section from the *Section* drop-down list.

**Note** The section must already exist in the selected document. You cannot create a section in the selected document at this point.

You can update links automatically or manually. See "Updating links" on page 29.

#### Write-protecting sections

To write-protect the current section so that its contents cannot be edited, check the **Protect** check box in the *Write protection* area (Figure 28).

Write protection	
With password	

Figure 27: Write-protecting sections


**Note** Write-protection protects only the section's contents, not its attributes or format.

#### **Password-protecting sections**

To prevent others from editing the section's attributes or format, protect the section with a password, as follows:

- 1) Check the **With password** check box. The Enter Password dialog box (Figure 28) opens.
- 2) Type a password in the *Password* field and then confirm the password by typing it again in the *Confirm* field.
- 3) Click **OK**. The Enter Password dialog box closes. Anyone who tries to edit the section's attributes or format will be prompted to enter the password.

Enter Passwor	d	X
<u>P</u> assword ⊆onfirm	****	OK Cancel



**Note** Passwords must contain at least five characters. The **OK** button remains inactive until you have typed five characters.

#### **Hiding sections**

You can hide the current section so that it will not be displayed on the screen or printed. You can also specify conditions for hiding the section. For example, you can hide the section only from certain users.

**Note** You cannot hide a section if it is the only content on the page or if the section is in a header, footer, footnote, endnote, frame, or table cell.

To hide a section, check the Hide check box in the Hide area (Figure 29).

Hide Hide	
With Condition	

Figure 29: Hiding sections

To hide the section only under certain conditions, enter the desired conditions in the *With Condition* field. The syntax and operators that you use to enter conditions are the same ones that you use to enter formulas. For syntax and a list of operators, see Writer's online help under "**conditions**".

If the section is write-protected with a password, the password must be entered to hide or reveal the text.

**Note** Hiding text is not a secure way to stop someone else reading it. It will stop the casual reader but will not prevent someone who actively wants to find out what you have hidden—even if it is password protected.

### Using the Columns page

Use the *Columns* page of the Insert Section dialog box to format the current section into columns. This page is very similar to the Columns dialog box shown in Figure 13 on page 12. Please refer to that topic for details.

## Using the Indents page

Use the *Indents* page, pictured in Figure 30, to set indents in the right and left margins of the current section. Enter the desired left-margin indent in the *Before section* box. Enter the desired right-margin indent in the *After section* box. The preview box on the right-hand side of the page shows you how the section will look with the indents applied.

Insert Section	$\sim$
Section Columns Inder	Its Background Footnotes/Endnotes
Indent	
Before section	1.50cm 📚
After section	3.00cm 📚

Figure 30: Indenting sections

## Using the Footnotes/Endnotes page

Use the *Footnotes/Endnotes* page, pictured in Figure 31, to customize the current section's footnotes and endnotes.

#### **Customizing footnotes**

If you want the current section's footnotes to appear separately from the other footnotes in the document, check the **Collect at end of text** check box in the *Footnotes* area.

To number the current section's footnotes separately from the other footnotes in the document, follow these steps:

- 1) In the *Footnotes* area, make sure that the **Collect at end of text** check box is checked.
- 2) Check the **Restart numbering** check box.
- 3) If you want the section's footnotes to start at a number other than 1, enter the desired starting number in the *Start at* spin box.

Insert Se	nsert Section 📀						
Section	Columns	Indents	Background	Footnotes/En	dnotes		
Footno	ites Collec <u>t</u> at en	nd of text					
	<u>R</u> estart n	umbering					
	<u>S</u> tart at		1	Ŷ			
	Custom	n <u>f</u> ormat					
	Before			1, 2, 3,	~	Aft <u>e</u> r	
Endnot							_
	i <u>o</u> llect at en		n				
	<u>R</u> estart nu	mbering					
	<u>S</u> tart at		1	•			
	Custom	format					
	Before			i, II, III,	~	Aft <u>e</u> r	
			(	Insert	Cancel	Help	<u>R</u> eset

Figure 31: Setting footnotes and endnotes for sections

To edit the format of the section's footnotes, follow these steps:

- 1) In the *Footnotes* area, make sure that the **Collect at end of text** and **Restart numbering** check boxes are checked.
- 2) Check the Custom format check box.

- 3) From the drop-down list under and to the right of the **Custom format** check box, select a numbering format for the footnotes.
- 4) To add text to the selected numbering format, use the *Before* and *After* fields. For example, if you want the footnote numbers to be preceded by the word "Note" and followed by a colon, fill the *Before* and *After* fields like this:

Footnotes  Collect at end of text	
Restart numbering	
Start at	
Custom format	
Before Note 1, 2, 3, 🖌 After :	

Figure 32: Numbering footnotes for sections

#### **Customizing endnotes**

If you want the current section's endnotes to appear at the end of the section rather than at the end of the document, check the **Collect at end of section** check box in the *Endnotes* area.

To number the current section's endnotes separately from the other endnotes in the document, follow these steps:

- 1) In the *Endnotes* area, make sure that the **Collect at end of section** check box is checked.
- 2) Check the Restart numbering check box.
- 3) If you want the section's endnotes to start at a number other than 1, enter the desired starting number in the *Start at* spin box.

To edit the format of the section's endnotes, follow these steps:

- 1) In the *Endnotes* area, make sure that the **Collect at end of section** and **Restart numbering** check boxes are checked.
- 2) Check the Custom format check box.
- 3) From the drop-down list under and to the right of the **Custom format** check box, select a numbering format for the endnotes.
- 4) To add text to the selected numbering format, use the *Before* and *After* fields, as shown above for footnotes (Figure 32).

## Using the Background page

Use the *Background* page to add color or a graphic to the background of the current section. This page is similar to the Background pages for paragraphs, frames, tables, and other objects in OOo. For more information, refer to Chapter 7, "Working with Styles".

## Saving a new section

To save a new section so that it appears in your document, click the **Insert** button. The Insert Section dialog box closes and the new section appears in your document.

## **Editing and deleting sections**

You can edit a section's attributes and formatting, and you can also delete sections.

#### Selecting a section

To select the section that you want to edit or delete, follow these steps:

- From the main menu, choose Format > Sections. The Edit Sections dialog box (Figure 33) opens.
- 2) The name of the current section appears in the *Section* area, in the field above the list box. If you want to edit or delete a different section, click the name of the desired section in the list. The selected section becomes the current section, and its name appears in the field above the list box.

Edit Sections		
Section Section1	– Link – – – – – – – – – – – – – – – – – – –	 ОК
Section1	DDE Eile name Section Write protection Protected With password Hide With Condition Properties Editable in read-only docur	 Cancel Options Remove Help

Figure 33: Edit Sections dialog box

#### **Editing section attributes**

To rename the current section, simply type over its name in the Section area.

From the Edit Sections dialog box, you can also edit the current section's link, write-protect, and hide attributes. To learn how to edit these attributes, see:

"Linking sections" on page 22.

"Write-protecting sections" on page 23.

"Hiding sections" on page 23.

#### **Deleting sections**

To delete the current section, click the **Remove** button.

**Note** Writer will not prompt you to confirm the delete! To undo a delete, click the **Cancel** button.

#### Editing the format of a section

To edit the format of the current section, click the **Options** button. The Options dialog box (Figure 33) opens.

The Options dialog box has four tabbed pages: *Columns, Indents, Background*, and *Footnotes/Endnotes*. To learn how to use these pages, see:

"Using the Columns page" on page 24.

"Using the Indents page" on page 24.

"Using the Background page" on page 26.

"Using the Footnotes/Endnotes page" on page 25.

To reset a page to its most recently saved settings, click the **Reset** button.

To save your Options settings and return to the Edit Sections dialog box, click OK.

Columns Inde	ents Background	Footnotes/Ei	ndnotes		
Settings —					7
⊆olumns					
1 🚔					
Evenly dis	tribute contents <u>t</u>	o all columns			
Width and spa	acing				
Column	+	<u>1</u>	2	3	+
Width		*	\$	4.9	
Spacing			0	Å	
		Auto <u>W</u> idth			
Separator line					
Line	None	~			
Height	100%	\$			
Position	Тор	~			
Cosidon	Tob				

Figure 34. Options dialog box for sections

## **Updating links**

You can have Writer update linked sections automatically, and you can also update links manually.

#### Updating links automatically

The default behavior, whenever you open a document that contains links, is for Writer to prompt you to update the links. To have Writer update links without prompting you or to turn off automatic updating, follow these steps:

- Choose Tools > OpenOffice.org Writer > General. The dialog box displays general text document settings.
- 2) In the *Update* area (Figure 35), under *Update links when loading*, select one of the following three options:

Automatically
🗹 <u>F</u> ields
✓ Charts

*Figure 35: Writer > General options settings* 

- Select **Always** if you want Writer to update links automatically, without prompting you, whenever you open a document that contains links.
- Select **On request** if you want Writer to prompt you before updating links.
- Select Never if you do not want Writer to update links.
- 3) Click **OK** to save your settings. The Options dialog box closes.

#### **Updating links manually**

To update a link manually:

- 1) Open the document that contains the link.
- 2) Choose Edit > Links. The Edit Links dialog box opens. (See Figure 36.)
- 3) The list in the Edit Links dialog box displays the names of all the files that are linked to the current document. Click the file that corresponds to the link that you want to update.
- 4) Click the **Update** button. The most recently saved contents of the linked file appear in the current document.
- 5) To close the Edit Links dialog box, click Close.

Edit Links				
Source file	Element:	Туре	Status	
Anchoring%20exan	nples.sxw	Document	Manual	Help Update
				Modify Break Link
Source file	file:///C:/Documents and	d Settings/Jean Hollis Web	er/My Documents/OpenOffic	:e/user-guide
Element:				
Туре:	Document			
Update:	○ <u>A</u> utomatic	) Ma <u>n</u> ual		

Figure 36: Edit Links dialog box

## **Creating headers and footers**

Headers are portions of a document that always appear at the top of a page; footers appear at the bottom of a page. Typically, headers display the title or chapter name of a document. To insert a header, choose **Insert > Header**.




Figure 37: Inserting headers and footers

Similarly, to insert a footer, choose Footer.

Depending on which option you choose, an area will appear at the top or bottom of the page where you can enter text. This text will appear at the top or bottom of every page.

Items, such as document titles, chapter titles, and page numbers, which often go into headers and footers, are best added as fields. That way, if something changes, the headers and footers are all updated automatically. Fields are covered in Chapter 14, "Working with Fields", but one example here may be useful. To insert the document title into the header:

- 1) Select **File > Properties > Description**, enter a title for your document in the *Title* area, and click **OK** to close the dialog box.
- 2) Add a header (Insert > Header > Default).
- 3) Place the cursor in the header part of the page.
- 4) Select **Insert > Fields > Title**. The title should appear on a gray background (which does not show when printed and can be turned off).
- 5) To change the title for the whole document, choose **File > Properties > Description**.

## Portrait headers on landscape pages

When you define a header and footer on a landscape page, they will be aligned with the long side of the page. If your landscape pages are going to be inserted between portrait pages, you might want the headers and footers to be on the short sides of the landscape pages, so the final printed product looks like the contents of the landscape pages have been rotated 90 degrees on portrait pages.


You can set up portrait headers and footers on landscape pages by using a trick involving frames. These are a bit tedious to set up, but once you have done so, you can copy and paste them to other landscape pages. There does not appear to be a way to make this part of the landscape page style.

To set up portrait headers and footers on landscape pages:

1) Calculate the required margins so the text area of the landscape page is the same size as the text area on the portrait pages, taking into account the space for headers and footers on the portrait pages. For example, this book uses the margins shown in the following table. The landscape right and left margins are 1 cm larger than the portrait top and bottom margins, respectively. This difference accounts for the extra space used by the portrait header and footer (0.5 cm for the height of the header or footer and a 0.5 cm gap between the header or footer and the main text).

Portrait page (rigl	nt page)	Landscape pag	Landscape page (right page)				
Top margin	1.5 cm	Right margin	2.5 cm				
Bottom margin	1.5 cm	Left margin	2.5 cm				
Left (inner) margin	2.8 cm	Top margin	2.8 cm				
Right (outer) margin	1.8 cm	Bottom margin	1.8 cm				

- 2) Create the landscape page style.
- 3) Measure the distance from the upper and left edges of the page to the upper left-hand corner of the space where you want the footer to appear. Measure the width and length of the space the footer will occupy (to match footers on portrait pages). See Figure 38.



*Figure 38: Measuring the location and size of the footer frame* 

- 4) In a blank paragraph in the text, type the footer text or insert fields such as the page number or the chapter number and name—to match the footer text and fields on the portrait pages. Assign the *Footer* style to this paragraph so the typeface, font size, and tab settings match those of the footers on the portrait pages.
- 5) Select the text (including the fields) you just entered. Choose Format > Character. On the Character dialog box, choose the *Position* tab (Figure 39) and set *Rotation / Scaling* to 270 degrees (counter clockwise). Click OK.

Character					×
Font Font Effects	Position	Hyperlink	Backgro	ound	
Position					
Superscript	<u>R</u> a	ise/lower by	/	1%	Automatic
	Relative font size		size	100%	\$
🔘 Su <u>b</u> script				-	
Rotation / scaling -	<u>0 9</u> 0 c	legrees		degrees	Fit <u>t</u> o line
Scale <u>w</u> idth		100%	6 📚		

Figure 39: Rotating the footer text 270 degrees CCW

6) With the text still selected, choose **Insert > Frame**. In the Frame dialog box, choose the *Type* tab (Figure 40) and enter the width, height, and horizontal and vertical position for the footer.

Frame			$\mathbf{X}$
Type Options Wrap	Hyperlink Borders	Background Columns	Macro
Size		Anchor	
Width	0.50cm 📚	🔵 To <u>p</u> age	
Relatįve		💿 To paragrap <u>h</u>	
Automatic		🔘 To cha <u>r</u> acter	
Height (at least)	16.40cm 📚	◯ <u>A</u> s character	
Relative			
Auto <u>S</u> ize			
Keep ratio			
Position			
Horizontal From	left 🔽 by	1.50cm 🚖 <u>t</u> o	Entire page 🛛 💌
Mirror on even	pages		
Vertical Top	V by	0.00cm 🔅 to	Page text area 💌

Figure 40: Defining the size and position of the footer frame

If your footer has a line above the text, as in this book, on the *Borders* page (Figure 41), select a right border and specify the line width and spacing to the frame's contents.

Frame					×
Type Options Wrap Hype	erlink Borders	Background	Col	umns Macro	
Line arrangement	Line		_	Spacing to co	ntents
<u>D</u> efault	Style			Left	0.05cm 😂
	- None -	— 0.05 pt	^	Right	0.05cm 😂
User-defined		— 0.50 pt		Тор	0.05cm 😂
- <u>-</u>		- 1.00 pt 2.50 pt		Bottom	0.05cm 🜲
	4.00 pt	•	~	Synchronize	
	⊆olor				
	Black		~		

Figure 41: Specifying the border position, line width, and spacing to contents

8) Click **OK** to save these settings. The footer should now appear in the required position and orientation.

Repeat these steps (using appropriate measurements) to set up a portrait header on the landscape page.

## **Numbering pages**

To automatically number pages:

- 1) Insert a header or footer, as described in "Creating headers and footers" on page 30.
- 2) Place the cursor in the header or footer where you want the page number to appear and choose **Insert > Fields > Page Number**.

### Including the total number of pages

To include the total number of pages (as in page 1 of 12):

- 1) Type the word *page* and a space; then insert the page number as above.
- 2) Press the spacebar once, type the word *of* and add a space; then choose Insert > Fields > Page Count.
- **Note** The *Page Count* field inserts the total number of pages in the document, as shown on the *Statistics* page of the document's Properties dialog box (**File > Properties**). If you restart page numbering anywhere in the document, then the total page count may not be what you want. See "Problems with restarting page numbering" on page 36.

## **Restarting page numbering**

Often you will want to restart the page numbering at 1, for example, on the page following a title page or a table of contents. In addition, many documents have the *front matter* (such as the table of contents) numbered with Roman numerals and the main body of the document numbered in Arabic numerals, starting with 1.

You can restart page numbering in two ways.

#### Method 1:

- 1) Place the cursor in the first paragraph of the new page.
- 2) Choose Format > Paragraph.
- 3) On the *Text Flow* page of the Paragraph dialog box (Figure 9 on page 7), check **Insert** in the *Breaks* area.
- 4) In the *Type* drop-down list, select Page.
- 5) In the *Position* drop-down list, select **Before** or **After** to position where you want to insert the page break.
- 6) Check With Page Style and specify the page style to use.
- 7) Specify the page number to start from and then click OK.

#### Method 2:

- 1) Place the cursor in the first paragraph of the new page.
- 2) Choose Insert > Manual break.
- 3) Page break is the default selected on the Insert Break dialog box (Figure 42).

Insert Break	×
Type	ОК
◯ <u>C</u> olumn break	Cancel
⊙ <u>P</u> age break <u>S</u> tyle	Help
Default 💌	
🗹 Change page number	
1	

Figure 42: Restarting page numbering after a manual page break

- 4) Choose the required page in the Style drop-down list.
- 5) Check Change page number.
- 6) Specify the page number to start from and then click **OK**.

### Changing the format of page numbers

To set the page number to display in Roman numerals, you need to specify the format of numbers in the page style.

On the *Page* page of the Page Style dialog box, in the *Layout settings* section (Figure 43), select **i**, **ii**, **iii**, ... from the *Format* drop-down list.

Layout settings	
Page la <u>v</u> out	Right and left 🛛 💉
For <u>m</u> at	1, 2, 3,
Register-true	A, B, C, a, b, c,
	a, b, c,
Reference <u>S</u> tyle	I, II, III,
	i, ii, iii, 1, 2, 3,
	Nopo
	NOLE

Figure 43: Changing format of page numbers

### Problems with restarting page numbering

Restarting page numbering may lead to two problems.

- The *Statistics* page in the document's **Properties** (**File** > **Properties**) always displays the total number of pages in the document, which may not be what you want to appear in the *Page Count* field.
- When page numbering is restarted, OOo always make sure that an odd-numbered page is a right page and an even-numbered page is a left page. It does this by inserting a blank page, if necessary. Sometimes this blank page is not desired, particularly when creating PDFs or when printing single sided.

#### Solving the page count problem

Suppose you know exactly how many pages are not to be included in the page count. (You want one page to be excluded in the page count for the following example.)

Instead of inserting a Page Count field, you can do the following:

- 1) Position the cursor where you want the page count to appear.
- 2) Press *F2* to open the formula bar, just above the horizontal ruler in the main Writer window (see Figure 44).

		)efau	ılt			~		Time	s N	lew F	lom	nan		~
Т	ext fo	ormul	а	fø	•	×	¢	=	paç	je -1		)		
	1	• 1		ι··Σ	ζ.	۰ <u>۰</u>	1	÷	•	· <u>1</u> 2		1	з _	•
Figu	re 4	4:1	For	mula	ba	ır								

- 3) After the equal sign, type *page* -1. If you want to exclude multiple pages, substitute the number of excluded pages for 1 in the formula.
- 4) Press *Enter* to close the formula bar and insert the resulting field into the document.

If you do not know the total number of pages in advance, then one approach is to create a set reference on the last page and then insert a cross reference to it. (Refer to Chapter 14, "Working with Fields", for more information on setting references and inserting cross references.)

To create a set reference on the last page:

- 1) Go to the last page (*Ctrl+End*).
- 2) Choose **Insert > Cross-reference**.
- 3) On the *References* page of the Fields dialog box (Figure 45), select **Set Reference** in the *Type* column.

Fields			2
Document References	Functions DocInformation	Variables Database	
Type Set Reference Insert Reference Bookmarks	Selection	Format	
		Insert Close Help	

Figure 45: Setting a reference on the last page of the document

- 4) In the *Name* box, enter LastPage.
- 5) Click Insert. LastPage is now listed in the Selection column.

To insert a cross-reference to the last page in the header or footer where you want to refer to the total number of pages:

- 1) Position the cursor at the desired location—for example after the space added after of in the header or footer, as in page xx of yy.
- 2) Choose Insert > Cross-reference.
- 3) On the *References* page of the Fields dialog box (Figure 46), select **Insert Reference** in the *Type* column and **LastPage** in the *Selection* column. **LastPage** now appears in the *Name* box.
- 4) In the *Format* column, select As page style. Click Insert.

Notes Do not delete the reference set at the end of the document. If you do, the cross-reference will not work.If a field, such as a cross-reference, does not automatically update, select the text containing the field and press *F9*.

Fields		$\overline{\mathbf{X}}$
Document References	Functions DocInformation	Variables Database
<u>T</u> ype	Selection	Format
Set Reference Insert Reference Bookmarks	LastPage	Page Chapter Reference Above/Below As Page Style
		Insert Close Help

Figure 46: Inserting a cross-reference to the last page of a document

## Numbering portrait and landscape pages

To create page numbers on portrait and landscape pages in the same place and orientation:

- 1) Refer to "Portrait headers on landscape pages" on page 31 to create a landscape page style and landscape header or footer styles. When creating the page style, check the **Use dynamic spacing** check box in the *Spacing* area in the *Header* or *Footer* pages of the Page Style dialog box.
- 2) Insert the page break and choose the landscape page style; do not change the page numbering.
- In the relevant header or footer, insert the page number field (Insert > Fields > Page Number).

## Numbering the first page something other than 1

Sometimes you may want to start a document with a page number greater than 1. For example, you may be writing a book, with each chapter in a separate file. Chapter 1 may start with page 1, but Chapter 2 could begin with page 25 and Chapter 3 with page 51.

Follow these instructions to start the page numbering in a document at a number greater than 1. (These instructions are for a page number in a footer, but you could use a header instead.)

- **Tip** Do not set a starting page number that is an even number because you will end up with a blank page before the first page when you print the file or export it as a PDF.
  - Choose Insert > Footer > [page style] to activate the footer. (If the page style is already checked in the Footer menu, point to it and click OK in the OpenOffice.org 2.0 dialog box that appears. Then point to that page style again to select it.)
  - The cursor is now in the footer. To insert the page number, choose Insert > Fields > Page Number. The page number will be 1.
  - 3) Click in the first paragraph in the text area or type a paragraph of text.
  - 4) Choose **Format > Paragraph** (or right-click and choose **Paragraph** from the pop-up menu) to display the Paragraph dialog box.
  - 5) On the *Text Flow* page (Figure 9 on page 7), in the *Breaks* section, select **Insert** and select **Page** in the *Type* drop-down list. Select **With Page Style** and the page style you are using for the first page of the document.
  - 6) The *Page number* field is now active. Type the page number you want to start with. Click **OK** to close the Paragraph dialog box.

## Numbering pages by chapter

Technical documents often include the chapter number with the page number in the header or footer. For example, 1-1, 1-2, 1-3, ...; 2-1, 2-2, 2-3, ...

To set up this type of page numbering in OOo, you need to do three things:

- 1) Ensure that your chapter titles are all identified by the same paragraph style, for example, the Heading1 style.
- 2) Use **Tools > Outline Numbering** to tell OOo what paragraph style you are using for Level 1 in your outline, and specify "1,2,3" in the Number box. (See Figure 47.)
- 3) Insert the chapter number in your document. To do this:
  - a) Place the cursor in the header or footer just before the page number you inserted earlier, and choose **Insert > Fields > Other** from the menu bar.
  - b) On the Fields dialog (Figure 48), go to the *Document* page. Select **Chapter** in the *Type* list, **Chapter number** in the *Format* list, and **1** in the *Layer* box. Click **Insert**.
  - c) Type a hyphen or other punctuation between the chapter number and the page number.

For more information, see "Choosing paragraph styles for outline levels" and "Including chapter or section information in page headers" in Chapter 7, "Working with Styles".

#### Numbering pages

7		Outline Number	ing		X
Numbering	Position				
Level	Numbering				
1	<u>P</u> aragraph Style			1 Heading 1	
2 3	Heading 1		\$	Heading 2	
4	Number	1, 2, 3,	\$	Heading 3	
5	Character Style	None	\$	Heading 4	
7		None		Heading 5	
8	Sho <u>w</u> sublevels		* <b>&gt;</b>	Heading 6	
10	Separator			Heading 7	
1 - 10	<u>B</u> efore			Heading 8	
	<u>A</u> fter			Heading 9	
	<u>S</u> tart at	1	~	Heading 10	
	<i>a</i>				
		OK	Forma	t Cancel <u>H</u> elp <u>R</u> ese	t
		1 ОК	÷ Eorma	Heading 10	ese

Figure 47: Specifying paragraph style and numbering for chapter titles

2		Fields	5		X
Document Refere	nces Functions	DocInformation	Variables Da	atabase	
<u>Т</u> уре	S	elect	1	F <u>o</u> rmat	
Author Chapter Date File name Page Sender Statistics Templates Time				Chapter name Chapter number Chapter number and name Chapter number without sepa	
<b>F</b> : 40 <b>J</b> - 4	1	1 ( 11		<u>I</u> nsert <u>C</u> lose <u>H</u> elp	

Figure 48: Inserting a chapter number field